

[Home](#)

CLASSES

- rcb

endScript

getBoardId

getBoardVersion

getFirmwareVersion

onKeyPress

setDebugMode

wait
- console

append

clear

error

overwrite

print

remove

setVerbose

warning
- files

appendToFile

newLogEntry

newLogFile

newTextFile
- output

ramp

set

steps

steps2
- sensors

averageResultsArray

read

readOhm

setMotorPoles

setSafetyLimit

tareCurrent

tareLoadCells
- udp

ab2str

init

onReceive

send

str2ab

GLOBAL

output

rcb.output

`new output()`

Output control interface functions.

Source:

[rcbApi.js, line 457](#)

Methods

`(static) ramp(outputId, from, to, duration, callback)`

Smoothly ramps up or down the pwm signal. For safety reasons, will only work if the output was previously activated using the `rcb.output.set` function. To cancel/update a ramp in progress, simply call this function again with new parameters. For example if you want to stop the ramp with the output at 1000us, call: `rcb.output.ramp("esc", 1000, 1000, 0, null)`; Note that only one control function can be used simultaneously. You must wait for the ramp/steps function to start another.

Parameters:

Name	Type	Description
outputId	string	outputId - "esc", "servo1", "servo2", "servo3", "escA", "escB", "servoA", "servoB". escA, servoA, escB, servoB are for the Series 1780 coaxial channels. For the mono version of Series 1780, use the A side. Can also be an array of multiple outputs eg. ["escA","servoA"].
from	number	Ramp starting value between 0 and 2300 microseconds. Must be an array if the first parameter is also an array.
to	number	Ramp finishing value between 0 and 2300 microseconds. Must be an array if the first parameter is also an array.

[Home](#)

CLASSES

- rcb
 - endScript
 - getBoardId
 - getBoardVersion
 - getFirmwareVersion
 - onKeyPress
 - setDebugMode
 - wait
- console
 - append
 - clear
 - error
 - overwrite
 - print
 - remove
 - setVerbose
 - warning
- files
 - appendTextFile
 - newLogEntry
 - newLogFile
 - newTextFile
- output
 - ramp
 - set
 - steps
 - steps2
- sensors
 - averageResultsArray
 - read
 - readOhm
 - setMotorPoles
 - setSafetyLimit
 - tareCurrent
 - tareLoadCells
- udp
 - ab2str
 - init
 - onReceive
 - send
 - str2ab

GLOBAL

Name	Type	Description
duration	number	The duration of the ramp in seconds.
callback	rampDone	Function to execute when the ramp is finished.

Source: [rcbApi.js, line 620](#)

Examples

```
//Illustrates the use of the ramp function
rcb.console.print("Initializing ESC...");
rcb.output.set("esc",1000);
rcb.wait(callback, 4);

function callback(){
  var from = 1000;
  var to = 1400;
  var duration = 15;
  var done = rcb.endScript;
  rcb.output.ramp("esc", from, to, duration, done);
}

//Same as example above but with multiple outputs simultaneously
rcb.console.print("Initializing ESC...");
var outputs = ["escA","escB"];
var minVal = [1000,1000];
var maxVal = [1400,1300];
rcb.output.set(outputs,minVal);
rcb.wait(callback, 4);

function callback(){
  var duration = 15;
  var done = rcb.endScript;
  rcb.output.ramp(outputs, minVal, maxVal, duration, done);
}
```

(static) set(outputId, value, protocol_{opt})

Sets the control output. The first time calling this function the protocol must be specified to activate the output.

Parameters:

Name	Type	Attributes	Description

[Home](#)

CLASSES

- rcb

 - endScript
 - getBoardId
 - getBoardVersion
 - getFirmwareVersion
 - onKeyPress
 - setDebugMode
 - wait
- console

 - append
 - clear
 - error
 - overwrite
 - print
 - remove
 - setVerbose
 - warning
- files

 - appendTextFile
 - newLogEntry
 - newLogFile
 - newTextFile
- output

 - ramp
 - set
 - steps
 - steps2
- sensors

 - averageResultsArray
 - read
 - readOhm
 - setMotorPoles
 - setSafetyLimit
 - tareCurrent
 - tareLoadCells
- udp

 - ab2str
 - init
 - onReceive
 - send
 - str2ab

GLOBAL

Name	Type	Attributes	Description
outputId	string		"esc", "servo1", "servo2", "servo3", "escA", "escB", "servoA", "servoB". escA, servoA, escB, servoB are for the Series 1780 coaxial channels. For the mono version of Series 1780, use the A side. Can also be an array of multiple outputs eg. ['escA','servoA'].
value	number		range depends on the protocol used. Must be an array if the first parameter is also an array. Any value outside the protocol's supported range will turn off the output. See the Utilities tab to learn more about the available control protocols and their respective value ranges.
protocol	boolean	<optional>	If using the external RCbenchmark control board you can switch the protocol to one of these: "pwm_50", "pwm_100", "pwm_200", "pwm_300", "pwm_400", "pwm_500", "dshot150", "dshot300", "dshot600", "dshot1200", "multishot", "oneshot42", "oneshot125".

Source: [rcbApi.js, line 486](#)

Example

```
// Activate the PWM output
rcb.output.set("esc", 1000);
rcb.wait(callback1, 4);

// Setting outside the valid range (700-2300 for pwm) will turn
function callback1(){
  rcb.output.set("esc", 3000);
  rcb.wait(callback2, 4);
}

// You can switch control protocol if using the RCB control board
// https://www.rcbenchmark.com/products/series-1580-1585-rc-controller
```

Home

CLASSES

- rcb
- endScript

getBoardId

getBoardVersion

getFirmwareVersion

onKeyPress

setDebugMode

wait

- console
- append

clear

error

overwrite

print

remove

setVerbose

warning

- files
- appendTextFile

newLogEntry

newLogFile

newTextFile

- output
- ramp

set

steps

steps2

- sensors
- averageResultsArray

read

readOhm

setMotorPoles

setSafetyLimit

tareCurrent

tareLoadCells

- udp
- ab2str

init

onReceive

send

str2ab

GLOBAL

output - Documentation

```
function callback2(){
  rcb.output.set("esc", 0, "dshot150");
  rcb.wait(callback3, 4);
}

function callback3(){
  rcb.output.set("esc", 500);
  rcb.wait(rcb.endScript, 4);
}
```

(static) steps(outputId, from, to, steps, callback_{opt})

NOTE: Consider the steps2 function instead, which has a few extra features like a cooldown time. Steps up or down the pwm signal allowing you to perform tasks between each step. For safety reasons, will only work if the output was previously activated using the rcb.output.set function. Note that only one control function can be used simultaneously. You must wait for the steps/ramp function to finish to start another.

Parameters:

Name	Type	Attributes	Description
outputId	string		outputId - "esc", "servo1", "servo2", "servo3", "escA", "escB", "servoA", "servoB". escA, servoA, escB, servoB are for the Series 1780 coaxial channels. For the mono version of Series 1780, use the A side. Can also be an array of multiple outputs eg. ['escA','servoA'].
from	number		Steps starting value between 0 and 2300 microseconds. Must be an array if the first parameter is also an array.
to	number		Steps finishing value between 0 and 2300 microseconds. Must be an array if the first parameter is also an array.
steps	integer		Number of steps to perform.

[Home](#)

CLASSES

- rcb
 - endScript
 - getBoardId
 - getBoardVersion
 - getFirmwareVersion
 - onKeyPress
 - setDebugMode
 - wait

- console
 - append
 - clear
 - error
 - overwrite
 - print
 - remove
 - setVerbose
 - warning

- files
 - appendTextFile
 - newLogEntry
 - newLogFile
 - newTextFile

- output
 - ramp
 - set
 - steps
 - steps2

- sensors
 - averageResultsArray
 - read
 - readOhm
 - setMotorPoles
 - setSafetyLimit
 - tareCurrent
 - tareLoadCells

- udp
 - ab2str
 - init
 - onReceive
 - send
 - str2ab

GLOBAL

Name	Type	Attributes	Description
callback	stepDone	<optional>	Function to execute when a step finishes. This function should introduce some sort of delay for the steps function to be effective.

Source: [rcbApi.js, line 724](#)

Example

```
//Illustrates the use of the steps function
rcb.console.print("Initializing ESC...");
rcb.output.set("esc",1000);
rcb.wait(callback, 4);
var sensorPrintId;

function callback(){
    var from = 1000;
    var to = 1400;
    var steps = 10;
    rcb.output.steps("esc", from, to, steps, stepFct);
}

//Function called at every step
function stepFct(lastStep, nextStepFct){
    if(lastStep){
        rcb.endScript();
    }else{
        rcb.console.setVerbose(false);
        rcb.wait(function(){ //2 seconds settling time

            //Do stuff here... (record to log file, calculate speed, etc)
            rcb.sensors.read(readDone);

        }, 2);
    }
}

//Function called when read complete
function readDone(result){
    var speed = result.motorElectricalSpeed.displayValue;
    var unit = result.motorElectricalSpeed.displayUnit;
    if(sensorPrintId === undefined) sensorPrintId = rcb.console.printId;
    rcb.console.overwrite("Motor Speed: " + speed + " " + unit);

    //When done working, go to the next step
    rcb.console.setVerbose(true);
    nextStepFct();
}
}
```

(static) steps2(outputId, from, to, steps, stepCallback, finishedCallback, params_{opt})

[Home](#)

CLASSES

- rcb

endScript

getBoardId

getBoardVersion

getFirmwareVersion

onKeyPress

setDebugMode

wait
- console

append

clear

error

overwrite

print

remove

setVerbose

warning
- files

appendTextFile

newLogEntry

newLogFile

newTextFile
- output

ramp

set

steps

steps2
- sensors

averageResultsArray

read

readOhm

setMotorPoles

setSafetyLimit

tareCurrent

tareLoadCells
- udp

ab2str

init

onReceive

send

str2ab

GLOBAL

Compared to the steps function, the steps2 function has built-in cooldown time, settling time, and signal rate limiting. Steps up or down the pwm signal allowing you to perform tasks between each step. For safety reasons, will only work if the output was previously activated using the rcb.output.set function. Note that only one control function can be used simultaneously. You must wait for the steps/ramp function to finish to start another. You can set the "from" value higher than the "to" value, in which case the steps will go downwards. Important: the rate limiting is only between the steps. You should bring the throttle up to the correct throttle yourself and bring it back down yourself external to this function.

Parameters:

Name	Type	Attributes	Description
outputId	string		outputId - "esc", "servo1", "servo2", "servo3", "escA", "escB", "servoA", "servoB". escA, servoA, escB, servoB are for the Series 1780 coaxial channels. For the mono version of Series 1780, use the A side. Can also be an array of multiple outputs eg. ['escA','servoA'].
from	number		Steps starting value between 0 and 2300 microseconds. Must be an array if the first parameter is also an array.
to	number		Steps finishing value between 0 and 2300 microseconds. Must be an array if the first parameter is also an array.
steps	integer		Number of steps to perform.

[Home](#)

CLASSES

- rcb

endScript

getBoardId

getBoardVersion

getFirmwareVersion

onKeyPress

setDebugMode

wait
- console

append

clear

error

overwrite

print

remove

setVerbose

warning
- files

appendTextFile

newLogEntry

newLogFile

newTextFile
- output

ramp

set

steps

steps2
- sensors

averageResultsArray

read

readOhm

setMotorPoles

setSafetyLimit

tareCurrent

tareLoadCells
- udp

ab2str

init

onReceive

send

str2ab

GLOBAL

Name	Type	Attributes	Description
stepCallback	stepCallback		Function to execute when a step finishes. This function should introduce some sort of delay for the steps function to be effective (by calling the nextStep function).
finishedCallback	finishedCallback		Function to execute when the steps are all done.

[Home](#)

CLASSES

rcb	endScript getBoardId getBoardVersion getFirmwareVersion onKeyPress setDebugMode wait
console	append clear error overwrite print remove setVerbose warning
files	appendTextFile newLogEntry newLogFile newTextFile
output	ramp set steps steps2
sensors	averageResultsArray read readOhm setMotorPoles setSafetyLimit tareCurrent tareLoadCells
udp	ab2str init onReceive send str2ab

GLOBAL

Name	Type	Attributes	Description
params	Object	<optional>	Optional parameters: {steps_qty: default=5, settlingTime_s: default=2, cooldownTime_s: default=0, cooldownThrottle_us: default=from, cooldownMinThrottle: default=0, max_slew_rate_us_per_s: default=100}. Some motors heat up quickly, and may require a cooldown period between steps. You can also optionally specify the throttle at which to cooldown. When activating the cooldown function, the time to complete a test dramatically increases. For this reason the cooldownMinThrottle setting lets the cooldown activate only at high throttle (by default all steps are followed by a cooldown step). Some motors can generate too much torque from step inputs, and some power supplies will not tolerate a motor spinning down quickly. For this reason you can set a rate limit to the throttle signal. Zero disables the rate-limit feature.

Source: [rcbApi.js, line 785](#)

[Home](#)

CLASSES

- rcb
- endScript
 - getBoardId
 - getBoardVersion
 - getFirmwareVersion
 - onKeyboardPress
 - setDebugMode
 - wait

- console
- append
 - clear
 - error
 - overwrite
 - print
 - remove
 - setVerbose
 - warning

- files
- appendTextFile
 - newLogEntry
 - newLogFile
 - newTextFile

- output
- ramp
 - set
 - steps
 - steps2

- sensors
- averageResultsArray
 - read
 - readOhm
 - setMotorPoles
 - setSafetyLimit
 - tareCurrent
 - tareLoadCells

- udp
- ab2str
 - init
 - onReceive
 - send
 - str2ab

GLOBAL

Example

See the sample script called "Sweep - discrete V2" for usage sa

Documentation generated by [JSDoc 3.6.3](#) on Wed Aug 21 2019 09:49:26 GMT-0400 (Eastern Daylight Time) using the Minami theme.